



CTI-Client und Plantronics Headset

CTI-Client als Softphone aktiviert	
<p>Primäre Audiogeräte Einstellen: Aufs Zahnrad klicken Einstellungen Softphone- Einstellungen</p>	 <p>The screenshot shows the iWay.ch interface. A context menu is open over the gear icon in the top right. The menu items are: 'Infos zu CTI', 'Sprache', 'Einstellungen', 'Kontakte', 'Warteschleifen', 'Fax versenden', 'Abmelden', and 'Programm beenden'. The 'Einstellungen' item is selected, and a sub-menu is displayed with the following options: 'Benutzerdaten ändern', 'Softphone-Einstellungen', 'Hotkey konfigurieren', 'Animation beim Klingeln', 'Automatischer Status bei Inaktivität', 'Akustische Benachrichtigung bei Chat Nachricht', 'Status aus Outlook', 'Immer im Vordergrund', 'Statusfarbe für Gruppen/Sonderschaltungen', 'Drag and Drop ohne Ctrl = mit Rückfrage', 'Telefonverknüpfung', 'Gruppenanmeldungen', and 'Umleitungen konfigurieren'. The 'Softphone-Einstellungen' option is highlighted by the mouse cursor.</p>
<p>Die Audiogeräte Auswählen. "Headset Bedienelemente ansteuern" aktivieren</p>	 <p>The screenshot shows the 'Softphone Einstellungen' dialog box. It is divided into three sections: 'Primäre Audiogeräte', 'Sekundäre Audiogeräte', and 'Klingeltöne'. - 'Primäre Audiogeräte': Includes a description 'Diese Audiogeräte werden immer dann verwendet, wenn es sie Computer angeschlossen sind und darauf zugegriffen werden kann.' and three dropdown menus for 'Tonausgabe', 'Mikrofon', and 'Klingelausgabe', all set to 'Lautsprecher (Plantronics Savi 7xx)'. A checkbox 'Headset Bedienelemente ansteuern' is checked. - 'Sekundäre Audiogeräte': Includes a description 'Diese Audiogeräte werden dann verwendet, wenn die primären Audiogeräte nicht verfügbar sind. Die Angabe von sekundären Audiogeräten ist fakultativ.' and three dropdown menus for 'Tonausgabe', 'Mikrofon', and 'Klingelausgabe', all set to 'default - nicht verbunden'. A checkbox 'Headset Bedienelemente ansteuern' is checked. - 'Klingeltöne': Includes a description 'Liste der Audiogeräte aktualisieren' and three input fields for 'Klingelton intern', 'Klingelton Direkt', and 'Klingelton Gruppe', each with an 'Auswählen' button. The values are 'ring3.wav', 'ring1.wav', and 'ring6.wav' respectively. - 'Weiteres': Includes a 'Besetzt signalisieren, falls mehr als' dropdown set to '1' and a 'Gespräche aktiv sind' checkbox. There is also an unchecked checkbox 'Lautstärke des Mikrofons automatisch regeln'. At the bottom are 'Speichern' and 'Abbrechen' buttons.</p>

Downloaden und Installieren Sie die Plantronics Hub Software für Ihr Betriebssystem. Aktuelle Software: <https://www.plantronics.com>

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

Savi W720

Firmware ● All Components | View


Battery Level 100%

Connections ● PC
● Mobile Phone
● Savi Headset
● Conferenced Headsets: 0

Product ID AC01

Serial # 42CE002B628D42E0A48A4D66DDEA3C39 (Base)
B617B20296F1429BB68E1AA9CDB63A2 (Headset)

Reference [Overview](#) | [User Guide](#)



plantronics.

Klicken Sie auf Settings.

Audio Sensing

Stellen Sie die Funkverbindung zwischen der Basisstation und einem drahtlosen Headset automatisch her, wenn PC-Audio am USB-Anschluss erkannt wird, ohne die Anrufsteuerungstaste drücken zu müssen.

Auto-Answer (No Sensor)

Automatisches Beantworten eines eingehenden Anrufs, wenn das Headset aus der Ladestation entfernt wird. Wählen Sie Aus, um eingehende Anrufe durch Drücken der Anrufsteuerungstaste anzunehmen.

Default Phone Line

Stellen Sie die bevorzugte ausgehende Leitung ein, die verwendet werden soll, wenn Sie die Headset-Anrufsteuerungstaste drücken.

Aut

S

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

General

Configure things to work the way you do.

Savi W720 Cancel Apply

Audio Sensing
Automatically establish the radio link between the base and the wireless headset whenever PC audio is detected at the USB port, without having to press the call control button. On

Auto-Answer (No Sensor)
Automatically answer an incoming call when the headset is removed from the charge cradle. Set to Off to answer incoming calls by pressing the call control button. Off

Default Phone Line
Set the preferred outbound line to be used when you press the headset call control button. PC

Second Incoming Call
Control the ring behavior for an incoming call from a second communication pathway (e.g. an incoming mobile call when you are on an existing softphone call). Ring Once

Software Settings ⓘ

Headset to PC Radio Link Active Only During Call

plantronics.

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

the charge cradle. Set to On to answer incoming calls by pressing the call control button.

Default Phone Line
Set the preferred outbound line to be used when you press the headset call control button. PC

Second Incoming Call
Control the ring behavior for an incoming call from a second communication pathway (e.g. an incoming mobile call when you are on an existing softphone call). Ring Once

Software Settings ⓘ

Headset to PC Radio Link
Keep the radio link to the PC always active after the call has ended, eliminating the need to re-establish the radio link when switching between PC audio applications. Default behavior is an active link only during the call. Active Only During Call

Plantronics Product Improvement Program
Help us improve this software by allowing us to collect anonymous feature usage statistics. Off

Software Log Level
Adjust the amount of detail captured in the log files. Low

• Indicates device default setting.

Cancel Apply

plantronics.