



CTI-Client und Plantronics Headset

CTI-Client als Softphone aktiviert	
<p>Primäre Audiogeräte Einstellen: Aufs Zahnrad klicken Einstellungen Softphone- Einstellungen</p>	 <p>The screenshot shows the iWay.ch interface. A dropdown menu is open over the 'Einstellungen' (Settings) option. The 'Softphone-Einstellungen' (Softphone Settings) option is highlighted. The background shows a contact list with status indicators (green for 'Verfügbar', red for 'Nicht verfügbar').</p>
<p>Die Audiogeräte Auswählen. "Headset Bedienelemente ansteuern" aktivieren</p>	 <p>The screenshot shows the 'Softphone Einstellungen' dialog box. It is divided into sections for 'Primäre Audiogeräte' (Primary Audio Devices) and 'Sekundäre Audiogeräte' (Secondary Audio Devices). Both sections have dropdown menus for 'Tonausgabe' (Speaker), 'Mikrofon' (Microphone), and 'Klingelausgabe' (Ringtone). The 'Headset Bedienelemente ansteuern' checkbox is checked in both sections. Below these are fields for 'Klingeltöne' (Ringtones) with 'Auswählen' buttons. At the bottom, there is a 'Speichern' (Save) button and an 'Abbrechen' (Cancel) button.</p>

Downloaden und Installieren Sie die Plantronics Hub Software für Ihr Betriebssystem. Aktuelle Software: <https://www.plantronics.com>

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

Savi W720

Firmware ● All Components | View


Battery Level 100%

Connections ● PC
● Mobile Phone
● Savi Headset
● Conferenced Headsets: 0

Product ID AC01

Serial # 42CE002B628D42E0A48A4D66DDEA3C39 (Base)
B617B20296F1429BB68E1AA9CDB63A2 (Headset)

Reference [Overview](#) | [User Guide](#)



plantronics.

Klicken Sie auf Settings.

Audio Sensing

Stellen Sie die Funkverbindung zwischen der Basisstation und einem drahtlosen Headset automatisch her, wenn PC-Audio am USB-Anschluss erkannt wird, ohne die Anrufsteuerungstaste drücken zu müssen.

Auto-Answer (No Sensor)

Automatisches Beantworten eines eingehenden Anrufs, wenn das Headset aus der Ladestation entfernt wird. Wählen Sie Aus, um eingehende Anrufe durch Drücken der Anrufsteuerungstaste anzunehmen.

Default Phone Line

Stellen Sie die bevorzugte ausgehende Leitung ein, die verwendet werden soll, wenn Sie die Headset-Anrufsteuerungstaste drücken.

Aut

S

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

General

Configure things to work the way you do.

Savi W720 Cancel Apply

Audio Sensing
Automatically establish the radio link between the base and the wireless headset whenever PC audio is detected at the USB port, without having to press the call control button. On

Auto-Answer (No Sensor)
Automatically answer an incoming call when the headset is removed from the charge cradle. Set to Off to answer incoming calls by pressing the call control button. Off

Default Phone Line
Set the preferred outbound line to be used when you press the headset call control button. PC

Second Incoming Call
Control the ring behavior for an incoming call from a second communication pathway (e.g. an incoming mobile call when you are on an existing softphone call). Ring Once

Software Settings ⓘ

Headset to PC Radio Link Active Only During Call

plantronics.

Plantronics Hub

Device: Savi W720

About Settings Notifications Help

the charge cradle. Set to On to answer incoming calls by pressing the call control button.

Default Phone Line
Set the preferred outbound line to be used when you press the headset call control button. PC

Second Incoming Call
Control the ring behavior for an incoming call from a second communication pathway (e.g. an incoming mobile call when you are on an existing softphone call). Ring Once

Software Settings ⓘ

Headset to PC Radio Link
Keep the radio link to the PC always active after the call has ended, eliminating the need to re-establish the radio link when switching between PC audio applications. Default behavior is an active link only during the call. Active Only During Call

Plantronics Product Improvement Program
Help us improve this software by allowing us to collect anonymous feature usage statistics. Off

Software Log Level
Adjust the amount of detail captured in the log files. Low

• Indicates device default setting.

Cancel Apply

plantronics.